



MACH

Protocol Specification

Revision Date: 10/20/2016

Version: 1.2c

Proprietary Information of Miami International Holdings, Inc. and its subsidiaries.
Copyright © 2016 MIAX PEARL, LLC. All Rights Reserved.

Table of Contents

1	OVERVIEW	2
2	MACH PROTOCOL.....	2
2.1	PACKETS	2
2.2	MESSAGING.....	3
2.2.1	Start of Session.....	3
2.2.2	Heartbeats.....	3
2.2.3	Retransmissions	3
2.2.4	End of Session	3
2.3	DATA TYPES.....	3
2.4	PACKET HEADER STRUCTURE	4
3	PACKET TYPE AND STRUCTURE	4
3.1	SESSION LEVEL PROTOCOL PACKETS.....	4
3.1.1	Start of Session.....	4
3.1.2	Heartbeat	4
3.1.3	End of Session	5
3.2	APPLICATION DATA PACKETS.....	5
APPENDIX A: CONTACT LIST		6
APPENDIX B: REVISION HISTORY		7

1 Overview

In order to provide a robust and uniform session level protocol across all interfaces that require distribution of application messages, MIAX PEARL has created the MACH protocol.

MACH is a scalable and lightweight multicast based protocol that allows a publisher to publish to many subscribers. It incorporates session level communication and a packet structure that allows subscribers to detect gaps and know the start and end of a message session.

MACH features:

Scalability and Low latency: MACH uses multicast that allows the publisher to publish once and all subscribers to receive it without any degraded performance with addition of new subscribers. This results in a lower latency compared to any fan-out based solutions.

Increased performance: MACH bunches multiple MACH packets into a single UDP packet that reduces I/O calls at both ends allowing for increased I/O efficiency and performance.

Clear delineation from Application layer: MACH is designed to be used in conjunction with higher level application messaging protocols that specify the contents of the messages that MACH distributes. The MACH protocol layer is opaque to the higher-level messages permitting it to encapsulate and distribute an application message consisting of ASCII or binary data.

Link failure detection: Uses frequent heartbeats to enable subscribers to proactively detect link or publisher failures.

Note that MACH protocol does not provide any delivery guarantee. In case the subscriber detects a gap, publisher side applications are generally designed to have a separate retransmission service or redundant feeds. Refer to the publisher side application manual (example: Top of Market Feed) for additional details of availability of such services.

2 MACH Protocol


2.1 Packets

MACH Publisher distributes application data in the form of MACH packets. MACH packets contain a unique sequence number and each MACH channel has a unique multicast group and/or port.

While the MACH protocol limits the maximum payload length to 65,535 – (Header Size) bytes, publishing applications (example: Top of Market Feed) will keep the UDP packet size small and within the length of a standard MTU so as to get the best performance from the underlying infrastructure.

One or more MACH packets may be placed in the underlying Multicast MTU as the following two examples show:

Structure of the payload with one MACH Packet contained in a UDP packet



Structure of the payload with N (eg: 3) MACH packets contained in a UDP packet

One or more of such MACH messages can be buffered into a single UDP packet.



2.2 Messaging

2.2.1 Start of Session

A MACH session begins when the Publisher sends a *Start of Session* packet to denote that a new session has started. This is always the first packet in a session and every new session starts with a sequence number of 1.

Subscribers must be able to handle mid-day *start of session* messages from Publisher in case the Publisher needs to restart with a lower or higher sequence number.

2.2.2 Heartbeats

MACH uses heartbeat packets allowing subscribers to proactively detect link failures and Publisher failures. The Publisher must send a *heartbeat* packet anytime more than 1 second has passed since the Publisher last sent any data. This ensures that the subscribers will receive data on a regular basis. If the subscriber does not receive anything (neither data nor heartbeats) for an extended period of time (typically 3 heartbeat intervals), the link or the Publisher may be down.

2.2.3 Retransmissions

In case the subscriber detects a gap, publisher side applications are generally designed to have a separate retransmission service or redundant feeds. Refer to the publisher side application manual (example: Top of Market Feed) for additional details of availability of such services.

2.2.4 End of Session

The Publisher indicates that the current session has ended by sending an *End of Session* packet. This indicates that there will be no more packets contained in this session.

Subscribers must be able to handle mid-day *start of session* messages without the dissemination of an *end of session* message for the previous session from Publisher in case the Publisher experiences issues.

2.3 Data Types

The following table describes the data types used in MACH protocol:

Data Type	Description
BinaryU	Unsigned, little-endian byte-ordered, binary encoded numbers
BinaryS	Signed, little-endian byte-ordered, binary encoded numbers
Alphanumeric	Each byte can contain characters or numbers. Left justified and space-padded on to the right

2.4 Packet Header Structure

Field Name	Length	Data Type	Notes
Sequence Number	8	BinaryU	Sequence number of this data packet
Packet Length	2	BinaryU	Length of the packet. This includes the header and application data.
Packet Type	1	BinaryU	MACH protocol packet type.
			TypeDescription
			0Heartbeat
			1Start of Session
			2End of Session
3Application Data			
Session Number	1	BinaryU	The Session this packet was generated from

3 Packet Type and Structure

3.1 Session Level Protocol Packets

3.1.1 Start of Session

The Publisher will send a Start of Session packet to denote that a new session has started. This is always the first packet in a session.

Field Description (length is in bytes):

Field Name	Length	Data Type	Notes
Sequence Number	8	BinaryU	Sequence number of the next application data packet
Packet Length	2	BinaryU	Length of the packet.
Packet Type	1	BinaryU	Value of 1
Session Number	1	BinaryU	Current Session

3.1.2 Heartbeat

The Publisher will send a Heartbeat packet anytime more than 1 second passes where no data has been published. The subscriber can check if the link is lost if it does not receive anything for an extended period of time (e.g.: 3 Heartbeat intervals).

Heartbeat is sent with the sequence number of the last packet sent out. This will also help the subscriber in proactively recognizing if the last packet was lost.

Field Description (length is in bytes):

Field Name	Length	Data Type	Notes
Sequence Number	8	BinaryU	Sequence number of the last application data packet
Packet Length	2	BinaryU	Length of the packet.
Packet Type	1	BinaryU	Value of 0

Field Name	Length	Data Type	Notes
Session Number	1	BinaryU	Current Session

3.1.3 End of Session

The Publisher will send an End of Session packet to denote that the current session is finished. There will be no more packets disseminated in this session.


Field Description (length is in bytes):

Field Name	Length	Data Type	Notes
Sequence Number	8	BinaryU	Sequence number of the last application data packet
Packet Length	2	BinaryU	Length of the packet.
Packet Type	1	BinaryU	Value of 2
Session Number	1	BinaryU	Current Session

3.2 Application Data Packets

The Publisher application will send all messages as Sequenced data packets. The sequence number is unique for a given MACH session for a given multicast group/port pair. Each Sequenced data packet carries one application message from the higher-level protocol. The subscriber must use the sequence numbers to recognize missing packets (gaps) and out of order packets.

Structure of MACH message containing application data



Field Description:

Field Name	Length	Data Type	Notes
Sequence Number	8	BinaryU	Sequence number of this data packet
Packet Length	2	BinaryU	Length of the packet. Header and App Data
Packet Type	1	BinaryU	Value of 3
Session Number	1	BinaryU	Current Session
Application Message	Variable	Any	1 Application Message

Appendix A: Contact List

Please visit MIAX website at <http://www.MIAXOptions.com> for obtaining most up-to-date contact list and other such information.

Appendix B: Revision History

Revision Date	Version	Author	Description
Oct 07 2011	1.0	Vinay S. Rao	First official release.
Nov 10 2011	1.1	Kevin Mueller	Update MACH header
Jun 19 2012	1.2	Kevin Mueller	Update MACH Header 1) Increase the size of the Sequence number from 4 bytes to 8 bytes 2) Add a one byte Session Number
Feb 08 2013	1.2a	Kevin Mueller	Updated legal statement in footer
Sep 30 th , 2016	1.2b	Vinay S. Rao	Updated Logo and Copyright info.
Oct 20 th , 2016	1.2c	Vinay S. Rao	Fixed some typos in section 3.2